- This is a preview of Discussion 2 on Nov.4.
- You can read discussion\_2.pdf to know the content in advance.
- If you want to familiarize yourself with the simulator, the following content may be helpful.

For Windows/MacOS Users

- As IMUNES does not support Windows, you need to install a Linux/FreeBSD virtual machine.
- Ubuntu 18.04 will be used in class. You can download the ISO files of the OSes on:
  - NetEase Mirror Image Station (http://mirrors.163.com/ubuntu-releases/), or
  - ShanghaiTech EPAN (https://epan.shanghaitech.edu.cn/l/SFrhLE)
- VirtualBox is recommended to install the virtual machine.
  - Download VirtualBox (https://www.virtualbox.org/wiki/Downloads)
- Then, install VirtualBox, Ubuntu 18.04 and IMUNES according to following steps.

#### For Windows/MacOS Users


- Install VirtualBox
  - 1. Execute VirtualBox-xxxxxxxxxxxx















#### For Windows/MacOS Users

- Install Ubuntu 18.04 in VirtualBox
  - 1. Run VirtualBox





For Windows/MacOS Users



For Windows/MacOS Users



For Windows/MacOS Users




For Windows/MacOS Users




For Windows/MacOS Users

- Install Ubuntu 18.04 in VirtualBox
  - 8. Wait for installation to complete




9. Press **Enter,** input your password, **Unlock** 




Ubuntu has been installed now!


For All Ubuntu (including VM) Users

- Install IMUNES in Ubuntu 18.04
  - 1. Right click and Open Terminal




\* If you cannot open terminal, change the **Formats** and **Restart** the system, and login again






For All Ubuntu (including VM) Users


- Install IMUNES in Ubuntu 18.04
  - 2. Install software dependencies
    - 2.1. Obtain root privileges with command "su", and enter your password



- 2.2. Install dependencies with following command
  - apt install openvswitch-switch docker.io xterm wireshark make imagemagick tk tcllib util-linux




#### Press 'y' and Enter



For All Ubuntu (including VM) Users

- Install IMUNES in Ubuntu 18.04
  - 2. Install software dependencies
    - 2.2. Install dependencies (Continue)

Move to 'Yes' with keyboard ' $\leftarrow$ ', and **Enter** 



#### Complete

```
000
                            root@ubuntu: /home/vboxuser
File Edit View Search Terminal Help
Setting up libqgsttools-p1:amd64 (5.9.5-Oubuntu1) ...
Setting up openvswitch-common (2.9.8-Oubuntu0.18.04.5) ...
Setting up tcllib (1.19-dfsg-2) ...
Setting up wireshark-common (2.6.10-1~ubuntu18.04.0) ...
Setting up openvswitch-switch (2.9.8-Oubuntu0.18.04.5) ...
update-alternatives: using /usr/lib/openvswitch-switch/ovs-vswitchd to provide /
usr/sbin/ovs-vswitchd (ovs-vswitchd) in auto mode
Created symlink /etc/systemd/system/multi-user.target.wants/openvswitch-switch.s
ervice -> /lib/systemd/system/openvswitch-switch.service.
Setting up libgt5multimedia5-plugins:amd64 (5.9.5-Oubuntu1) ...
Setting up wireshark-qt (2.6.10-1~ubuntu18.04.0) ...
Setting up wireshark (2.6.10-1~ubuntu18.04.0) ...
Processing triggers for ureadahead (0.100.0-21) ...
Processing triggers for desktop-file-utils (0.23-1ubuntu3.18.04.2) ...
Processing triggers for libc-bin (2.27-3ubuntu1.4) ...
Processing triggers for systemd (237-3ubuntu10.52) ...
Processing triggers for man-db (2.8.3-2ubuntu0.1) ...
Processing triggers for shared-mime-info (1.9-2) ...
Processing triggers for gnome-menus (3.13.3-11ubuntu1.1) ...
Processing triggers for hicolor-icon-theme (0.17-2) ...
Processing triggers for mime-support (3.60ubuntu1) ...
root@ubuntu:/home/vboxuser#
```

#### For All Ubuntu (including VM) Users


- Install IMUNES in Ubuntu 18.04
  - 2. Install IMUNES with following commands
  - git clone https://github.com/imunes/imunes.git
  - cd imunes
  - make install

```
root@ubuntu:/home/vboxuser# git clone https://github.com/imunes/imunes.git
Cloning into 'imunes'...
remote: Enumerating objects: 5386, done.
remote: Counting objects: 100% (1962/1962), done.
remote: Compressing objects: 100% (372/372), done.
remote: Total 5386 (delta 1757), reused 1665 (delta 1590), pack-reused 3424 (fro m 1)
Receiving objects: 100% (5386/5386), 2.32 MiB | 1.08 MiB/s, done.
Resolving deltas: 100% (4005/4005), done.
root@ubuntu:/home/vboxuser# cd imunes
root@ubuntu:/home/vboxuser/fmunes#
```

```
root@ubuntu:/home/vboxuser/imunes# make install
rm -rf /usr/local/lib/imunes
for file in imunes pkg_imunes himage.linux vlink.tcl vlink apk_imunes hcp.linux
cleanupAll startxcmd himage cleanupAll.linux hcp apt-get_imunes startxcmd.linux;
do \
       rm -f /usr/local/bin/${file}; \
done ;
rm -rf /usr/local/etc/rc.d/imunes-service.sh
To remove startup topologies, remove /var/imunes-service
mkdir -p /usr/local/lib/imunes
cp COPYRIGHT README.md VERSION /usr/local/lib/imunes
ROOTDIR=/usr/local sh scripts/update_version.sh
mkdir -p /usr/local/bin
sed -e "s,set LIBDIR \"\",set LIBDIR lib/imunes," \
    -e "s,set ROOTDIR \".\",set ROOTDIR /usr/local," \
    imunes.tcl > /usr/local/lib/imunes/imunes.tcl
```

#### 2. Run IMUNES with following command

imunes



IMUNES has been installed!